

# Image classification

---

## Image classification

1. Enable optimal performance of the motherboard
  - 1.1. Enable MAX power mode
  - 1.2. Enable Jetson clocks
2. Image classification: Image  
Effect preview
3. Image classification: video  
Effect preview
4. Image classification: real-time detection
  - 4.1. USB camera  
Effect preview
  - 4.2. CSI camera  
Effect preview
- References

Using Python to demonstrate **Ultralytics**: Image classification in images, videos, and real-time detection.

## 1. Enable optimal performance of the motherboard

---

### 1.1. Enable MAX power mode

Enabling MAX Power Mode on Jetson will ensure that all CPU and GPU cores are turned on:

```
sudo nvpmodel -m 0
```

### 1.2. Enable Jetson clocks

Enabling Jetson Clocks will ensure that all CPU and GPU cores run at maximum frequency:

```
sudo jetson_clocks
```

## 2. Image classification: Image

---

Use yolo11n-cls.pt to predict images under the ultralytics project (not ultralytics built-in images).

Enter the code folder:


```
cd /home/jetson/ultralytics/ultralytics/yahboom_demo
```

Run the code:

```
python3 04.classification_image.py
```

## Effect preview

Yolo recognition output image location: /home/jetson/ultralytics/ultralytics/output/



Sample code:

```
from ultralytics import YOLO

# Load a model
model = YOLO("/home/jetson/ultralytics/ultralytics/yolo11n-cls.pt")

# Run batched inference on a list of images
results = model("/home/jetson/ultralytics/ultralytics/assets/dog.jpg") # return
a list of Results objects

# Process results list
for result in results:
    # boxes = result.boxes # Boxes object for bounding box outputs
    # masks = result.masks # Masks object for segmentation masks outputs
    # keypoints = result.keypoints # Keypoints object for pose outputs
    # probs = result.probs # Probs object for classification outputs
    # obb = result.obb # Oriented boxes object for OBB outputs
    result.show() # display to screen

    result.save(filename="/home/jetson/ultralytics/ultralytics/output/dog_output.jpg") # save to disk
```

## 3. Image classification: video

Use yolo11n-cls.pt to predict the video under the ultralytics project (not the video that comes with ultralytics).

Enter the code folder:


```
cd /home/jetson/ultralytics/ultralytics/yahboom_demo
```

Run the code:

```
python3 04.classification_video.py
```

## Effect preview

Yolo identifies the output video position: /home/jetson/ultralytics/ultralytics/output/



Sample code:

```
import cv2
from ultralytics import YOLO

# Load the YOLO model
model = YOLO("/home/jetson/ultralytics/ultralytics/yolo11n-cls.pt")

# Open the video file
video_path = "/home/jetson/ultralytics/ultralytics/videos/cup.mp4"
cap = cv2.VideoCapture(video_path)

# Get the video frame size and frame rate
frame_width = int(cap.get(cv2.CAP_PROP_FRAME_WIDTH))
frame_height = int(cap.get(cv2.CAP_PROP_FRAME_HEIGHT))
fps = int(cap.get(cv2.CAP_PROP_FPS))

# Define the codec and create a Videowriter object to output the processed video
output_path = "/home/jetson/ultralytics/ultralytics/output/04.cup_output.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))

# Loop through the video frames
while cap.isOpened():
    # Read a frame from the video
    success, frame = cap.read()
```

```

if success:
    # Run YOLO inference on the frame
    results = model(frame)

    # Visualize the results on the frame
    annotated_frame = results[0].plot()

    # Write the annotated frame to the output video file
    out.write(annotated_frame)

    # Display the annotated frame
    cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

    # Break the loop if 'q' is pressed
    if cv2.waitKey(1) & 0xFF == ord("q"):
        break
else:
    # Break the loop if the end of the video is reached
    break

# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()

```

## 4. Image classification: real-time detection

### 4.1. USB camera

Use yolo11n-cls.pt to predict the USB camera image.

Enter the code folder:


```
cd /home/jetson/ultralytics/ultralytics/yahboom_demo
```

Run the code: Click the preview image and press the q key to terminate the program!

```
python3 04.classification_camera_usb.py
```

### Effect preview

Yolo identifies the output video position: /home/jetson/ultralytics/ultralytics/output/



Sample code:

```
import cv2
from ultralytics import YOLO

# Load the YOLO model
model = YOLO("/home/jetson/ultralytics/ultralytics/yolo11n-cls.pt")

# Open the camera
cap = cv2.VideoCapture(0)

# Get the video frame size and frame rate
frame_width = int(cap.get(cv2.CAP_PROP_FRAME_WIDTH))
frame_height = int(cap.get(cv2.CAP_PROP_FRAME_HEIGHT))
fps = int(cap.get(cv2.CAP_PROP_FPS))

# Define the codec and create a VideoWriter object to output the processed video
output_path =
"/home/jetson/ultralytics/ultralytics/output/04.classification_camera_usb.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))

# Loop through the video frames
while cap.isOpened():
    # Read a frame from the video
    success, frame = cap.read()

    if success:
        # Run YOLO inference on the frame
        results = model(frame)

        # Visualize the results on the frame
        annotated_frame = results[0].plot()

        # Write the annotated frame to the output video file
```

```

out.write(annotated_frame)

# Display the annotated frame
cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

# Break the loop if 'q' is pressed
if cv2.waitKey(1) & 0xFF == ord("q"):
    break
else:
    # Break the loop if the end of the video is reached
    break
# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()

```

## 4.2, CSI camera

Use yolo11n-cls.pt to predict the CSI camera image.

Enter the code folder:


```
cd /home/jetson/ultralytics/ultralytics/yahboom_demo
```

Run the code: Click the preview image, press the q key to terminate the program!

```
python3 04.classification_camera_csi.py
```

## Effect preview

Yolo identifies the output video position: /home/jetson/ultralytics/ultralytics/output/



Sample code:

```
import cv2
```

```

from ultralytics import YOLO
from jetcam.csi_camera import CSICamera

# Load the YOLO model
model = YOLO("/home/jetson/ultralytics/ultralytics/yolo11n-cls.pt")

# Open the camera (CSI Camera)
cap = CSICamera(capture_device=0, width=640, height=480)

# Get the video frame size and frame rate
frame_width = 640
frame_height = 480
fps = 30

# Define the codec and create a Videowriter object to output the processed video
output_path =
"/home/jetson/ultralytics/ultralytics/output/04.classification_camera_csi.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))

# Loop through the video frames
while True:
    # Read a frame from the camera
    frame = cap.read()

    if frame is not None:
        # Run YOLO inference on the frame
        results = model(frame)

        # Visualize the results on the frame
        annotated_frame = results[0].plot()

        # Write the annotated frame to the output video file
        out.write(annotated_frame)

        # Display the annotated frame
        cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

        # Break the loop if 'q' is pressed
        if cv2.waitKey(1) & 0xFF == ord("q"):
            break
    else:
        # Break the loop if no frame is received (camera error or end of stream)
        print("No frame received, breaking the loop.")
        break

# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()

```

## References

<https://docs.ultralytics.com/tasks/classify/>

